

CTX-Quality-Control User Guide



Contents

CTX-(Quality-Control User Guide	1
Conte	ents	2
Versi	ons	3
Doo	cument Revisions	3
Mod	dule Versions	3
	ce	
	out this Manual	
	lience	
	ated Material	
	previations used in this Document	
•	irements	
_	ration	
	egration with Third-Party Systems	
	egrating with Existing Infrastructure	
1	Overview	
2	Configuration	8
3	UI Guide	9
4	Excel Report Generator1	1
5	Flows1	13
5.1	Co create i to i repertu	
5.1.1	Overview	13
5.1.2	Input variables	
5.2	Quality Causing	
	Overview	
5.2.2	Input variables	13
	Output variables	
5.3	Co from Corror Land Country	
	Overview	
	Input variables	
5.3.3	Output variables	
6	Troubleshooting1	
6.1		
6.2	Timeout	15



Versions

Document Revisions

The following revisions have been made to this document

Date	Revision	Notes
10/10/2019	1.0	First Release

Module Versions

The following revisions have been made to this document

Date	Revision	Notes
10/10/2019	1.0	First Release



Preface

About this Manual

This document is a user guide for the CTX-Quality-Control module.

Audience

The audience for this document is those wanting to understand how to use CTX-Quality-Control module.

Related Material

Document

CTX-Quality-Control - Deployment Plan

CTX-Quality-Control.studiopkg

Abbreviations used in this Document

SQL Structured Query Language



Requirements

The CTX-Quality-Control module requires the following:

- SQL Server 2016 or newer
- Minimum Cortex v6.5 installed on the Cortex Application Server
- Windows PowerShell v5 or later



Integration

Integration with Third-Party Systems

None Required.

Integrating with Existing Infrastructure

None Required.



1 Overview

The quality control module allows users to assess quality metrics for their flows based on the Cortex Best Practice Guidelines. For each flow the following metrics are calculated:

- Description coverage
- Number of time savings blocks
- Number of disconnected blocks
- Number of unused variables

A flow or subtask will be marked with a pass or fail based on the configured threshold for these metrics.

Flow quality can be assessed from a LivePortal flow (QC-View-Server-Flows-Quality) or through an Excel document that can be generated using the flow QC-Create-Flow-Report



2 Configuration

QualityControlConfig.txt contains the following parameters:

- DatabaseServer: The name of the server with the Cortex databases
- DatabaseName: The Cortex database containing the flow information, this should be CortexWeb
- PowerShellDomain: Domain of the PowerShell user, leave empty string if PowerShell block authentication isn't required
- PowerShellUser: PowerShell username, leave empty string if PowerShell block authentication isn't required
- PowerShellUser: PowerShell user password, leave empty string if PowerShell block authentication isn't required
- QualityControlPowerShellModulesPath: Path to quality control modules
- CortexRepositoriesPath: Path to cortex web repository
- DisconnectedBlocksThreshold: Threshold maximum number of disconnected blocks
- UnusedVariablesThreshold: Threshold maximum number of unused variables
- DescriptionCoverageThreshold: Threshold for the percentage of blocks that have descriptions
- TimeSavingsThreshold: Threshold for minimum number of time saving blocks
- StateErrorHandlersThreshold: Threshold for maximum number of state error handler blocks
- MailServer: Name of the mail server, required if you intend to send emails
- MailServerPort: Port of the mail server, required if you intend to send emails
- MailServer: Email address of the report sender, required if you intend to send emails



3 UI Guide

The UI will allow you to select a number of flows to be analysed and it will display the result of the analysis.

Start the UI interface by executing the service request named QC-View-Server-Flows-Quality within LivePortal. A list as shown in Figure 1 will be displayed. You can select a group of flows/subtasks, please note that nested groups are displayed with a '\'. All flows within a selected group will be tested, including flows contained within child groups.




Figure 1 - List of flow groups, flows and subtasks that can be selected for analysis

Once a group is selected the checks will begin to run, this may take a few minutes if lots of flows need to be processed. When the analysis ends, a page will be shown with an overview of the flows analysed as illustrated in Figure 2. You can select a flow or subtask and click View Report to see more details of their compliance with the quality standards.






Figure 2 - Result of the flows and subtasks analysis

The report view provides more specific information on disconnected blocks and unused variables as illustrated in Figure $\bf 3$




Figure 3 - Flow/subtask quality report



4 Excel Report Generator

This is the recommend method for viewing reports on large numbers of flows. The flow (QC-Create-Flow-Report) takes 3 inputs:

- i_Group: The group of flows/subtasks that you wish to evaluate. Nested groups should take the format: 'Cortex-Library\CTX-Quality-Control'
- i_Contacts: (Optional) CSV of emails to send the report to
- i_FileWritePath: The folder that you wish to save the report to

It is normally useful to create a scheduled flow that generates a report on a periodic basis. Cortex provides a UI to schedule flows as a GitHub module (CTX-Task-Scheduler) that can be found **here**.

The flow will create an Excel document, the first tab will show an Overview as displayed in Figure 4, click on a flow/subtask name will show a detailed view




Figure 4 - Flow and subtask analysis excel report overview tab



In Figure 5 you can see a detailed view of a specfic flow or subtask, it gives more information on the unused variables and disconnected blocks. The 'Back to Overview' link at the bottom of the tab will take you back to the overview page.




Figure 5 - Flow and subtask analysis excel report detailed report tab



5 Flows

5.1 QC-Create-Flow-Report

5.1.1 Overview

Creates an excel report, writes it to a file and emails it based on a given flow group

5.1.2 Input variables

Name	Туре	Comments	
i_Group	Text	The group of flows/subtasks that you wish to evaluate. Nested groups should take the format: 'Cortex-Library\CTX-Quality-Control'	
i_Contacts	Text	(Optional) CSV of emails to send the report to	
I_FileWritePath Text The folder that you		The folder that you wish to save the report to	

5.2 QC-Get-Group-Quality

5.2.1 Overview

Evaluates flow quality for a given group

5.2.2 Input variables

Name	Туре	Comments
i_Group	Text	The group of flows/subtasks that you wish to evaluate. Nested groups should take the format: 'Cortex-Library\CTX-Quality-Control'

5.2.3 Output variables

Name	Туре	Comments
o_Group-Quality	Structure	Structured data for group quality

5.3 QC-View-Server-Flows-Quality

5.3.1 Overview

LivePortal flow to display flow quality for a given group

5.3.2 Input variables

None

5.3.3 Output variables

None



6 Troubleshooting

6.1 Maximum message size

Failed to communicate with Cortex Powershell agent at localhost:22100. The following error occured:

System. Service Model. Communication Exception: The maximum message size quota for incoming messages (65536) has been exceeded.

This means that too much data is being passed through the PowerShell interface, you may experience this running large groups of flows. The maximum message size can be increased with the following steps:

- 1. Open C:\Program Files (x86)\Cortex\Cortex PowerShell Agent Service\Innovise.Cortex.Server.Api.PowerShell.Agent.exe.config
- 2. Under <services> find the <endpoint> with binding="netTcpBinding". Add name="netTcpBinding" to the tag and change the value of bindingConfiguration to "netTcpBinding". The opening <endpoint> tag should look similar to this:

- 3. Open C:\Program Files (x86)\Cortex\Cortex Generic Interface Service\Innovise.Cortex.Server.Host.exe.config
- 4. Between </startup> and <applicationSettings> insert the following:

5. Go to services and restart the Cortex Powershell Agent service and the Cortex Generic Interface service.



6.2 Timeout

Failed to communicate with Cortex Powershell agent at localhost:22100. The following error occured: System. Service Model. Communication Exception: The socket connection was aborted. This could be caused by an error processing your message or a receive timeout being exceeded by the remote host, or an underlying network resource issue

It is likely that the receive timeout on the Cortex PowerShell agent is too short. The receive timeout can be increased with the following steps:

- 1. Open C:\Program Files (x86)\Cortex\Cortex PowerShell Agent Service\Innovise.Cortex.Server.Api.PowerShell.Agent.exe.config
- 2. Find the recieveTimout attribute on the binding named netTcpBinding. Change the receiveTimeout value from its default value of 00:10:00 to 00:59:00 and save the file
- 3. Restart the Cortex PowerShell agent service